

Slider.mui

1. [Super class](#)
2. [Background](#)
3. [Attributes](#)
4. [MUIA_Slider_Horiz](#)
5. [MUIA_Slider_Level](#)
6. [MUIA_Slider_Max](#)
7. [MUIA_Slider_Min](#)
8. [MUIA_Slider_Quiet](#)
9. [MUIA_Slider_Reverse](#)

Slider.mui

Super class

[Numeric.mui](#)

Background

The slider class generates a GU element that allows a user to adjust a numeric value. The programmer has not very much influence on the slider's outfit, there are only very few tags available. Future versions of MUI will probably include some preferences options to allow the user (**NOT** the programmer) to configure this outfit.

Note that since slider is a subclass of group class, you can get horizontal or vertical sliders by simply using the [MUIA_Group_Horiz](#) attribute. Default is a horizontal slider.

Attributes

Attribute	Version	ISG	Type
MUIA_Slider_Horiz	V11	ISG	BOOL
MUIA_Slider_Level	V4	ISG	LONG (OBSOLETE)
MUIA_Slider_Max	V4	ISG	LONG (OBSOLETE)
MUIA_Slider_Min	V4	ISG	LONG (OBSOLETE)
MUIA_Slider_Quiet	V6	I..	BOOL
MUIA_Slider_Reverse	V4	ISG	BOOL (OBSOLETE)

MUIA_Slider_Horiz

NAME

[MUIA_Slider_Horiz](#) — V11 [ISG], BOOL, 0x8042fad1

FUNCTION

Specify if you want a horizontal or vertical slider. Also understands MUIA_Group_Horiz to be compatible with previous versions of MUI.

MUIA_Slider_Level

NAME

MUIA_Slider_Level — V4 [ISG], LONG, 0x8042ae3a (**OBSOLETE**)

FUNCTION

The current position of the slider knob. This value is guaranteed to be between MUIA_Slider_Min and MUIA_Slider_Max.

EXAMPLE

```
SliderObject
  MUIA_Group_Horiz FALSE
  MUIA_Slider_Min
  MUIA_Slider_Max
  MUIA_Slider_Level
End
```

SEE ALSO

MUIA_Slider_Min, MUIA_Slider_Max

MUIA_Slider_Max

NAME

MUIA_Slider_Max — V4 [ISG], LONG, 0x8042d78a (**OBSOLETE**)

FUNCTION

Adjust the maximum value for a slider object.

SEE ALSO

MUIA_Slider_Min, MUIA_Slider_Level

MUIA_Slider_Min

NAME

MUIA_Slider_Min — V4 [ISG], LONG, 0x8042e404 (**OBSOLETE**)

FUNCTION

Adjust the minimum value for a slider object. Of course you can use negative number, e.g. for a slider to adjust task priority.

SEE ALSO

MUIA_Slider_Max, MUIA_Slider_Level

MUIA_Slider_Quiet

NAME

MUIA_Slider_Quiet — V6 [I.], BOOL, 0x80420b26

FUNCTION

When set to TRUE, the slider doesn't display it's current level in a text object.

SEE ALSO

MUIA_Slider_Level

MUIA_Slider_Reverse

NAME

MUIA_Slider_Reverse — V4 [ISG], BOOL, 0x8042f2a0 (**OBSOLETE**)

FUNCTION

Setting this attribute to TRUE will reverse the direction of the slider.

SEE ALSO

MUIA_Slider_Min, MUIA_Slider_Max, MUIA_Slider_Level

Copyright © 1992-2006 by Stefan
Stuntz
Copyright © 2006-2018 by Thore
Böckelmann, Jens Maus

MUI for AmigaOS -
MUI-Autodocs

Updated: 06-Dec-2018